MIPSpro™ Compiling, Debugging, and Performance Tuning Guide

About This Guide

This guide describes the MIPSpro™ compiler system, the debugger, and other programming tools and interfaces. It also explains ways to improve program performance.

The IRIX compiler system produces either 64−bit object code or 32−bit object code. This guide describes the MIPSpro compilers that produce 64−bit objects. For information about compilers that produce 32−bit objects and how to debug them, refer to the *IRIX System Programming Guide* and *dbx User's Guide*, respectively.

What This Guide Contains

This guide contains the following chapters:

- **Chapter 1, "About the MIPSpro Compiler System,"** gives an overview of the MIPSpro compiler system.
- **Chapter 2, "Using the MIPSpro Compiler System,"** describes the components of the MIPSpro compiler system.
- **Chapter 3, "Using Dynamic Shared Objects,"** explains how to build and use dynamic shared objects.
- **Chapter 4, "Using the Debugger,"** covers how to use the source level debugger, *dbx*, to debug your programs.
- **Chapter 5, "Using the Performance Tools,"** describes how to use the profiling tool, *prof*, and how to obtain basic block counts with *pixie*.
- **Chapter 6, "Optimizing Program Performance,"** explains how to reduce program execution time by using optimization options and techniques.
- **Chapter 7, "Coding for 64−Bit Programs"** describes how to write or update code that is portable to 64−bit systems.

Some information about the IRIX operating system is covered in the *Indigo Magic Desktop Integration Guide*, namely fonts and internationalization.

What You Should Know Before Reading This Guide

This guide is for anyone who wants to program effectively using the MIPSpro compilers. We assume you are familiar with the IRIX (or UNIX®) operating system and a programming language such as C or Fortran. This guide does not explain how to write and compile programs.

This guide does not cover the differences between 64−bit compilation and 32−bit compilation modes. Refer to the *Application Porting and Transition Guide* for detailed information about the differences between these modes, language implementation differences, source code porting, compilation issues, and run−time execution.

Suggestions for Further Reading

This *Compiling, Debugging, and Performance Tuning Guide* is part of the IRIS Developer Option (IDO), which provides you with the software and documentation that you need to write applications for Silicon Graphics platforms. **Table In−1** lists the IDO online and printed manuals.

Table 0−1 IDO Topics and Manuals

Topic	Manual
IRIX Operating System	IRIX System Programming Guide
	IRIX Network Programming Guide

ANSI C and Compilation	Compiling, Debugging, and Performance Tuning Guide (MIPSpro compilers and debugger)
	C Language Reference Manual
Desktop Environment	Indigo Magic Desktop Integration Guide
	IRIS WorkSpace Integration Guide
Graphics	OpenGL Programming Guide
	OpenGL Porting Guide
X Window System	XLib Programming Manual (O'Reilly, Vol. 1)
	X Toolkit Intrinsics Programming Manual (O'Reilly, Vol. 4)
OSF/Motif	OSF/Motif Programmer's Guide
	OSF/Motif Reference Manual
	OSF/Motif Style Guide
	IRIS IM Programming Notes

To read the online manuals after installing them, type **`insight`** or double−click the InSight icon. It's easy to print sections and chapters of the online manuals from InSight. You can also order printed manuals from Silicon Graphics by calling SGI Direct at 1−800−800−SGI1 (800−7441). Outside the U.S. and Canada, contact your local sales office or distributor.

In addition to the IDO, Silicon Graphics offers software options to assist in your software development. The compiler options include *Fortran77*, *Power Fortran*, and *C++*. *CASEVision/Workshop* provides the WorkShop toolset: the Debugger, Static Analyzer, Performance Analyzer, Tester, and Build Manager.

You may also want to learn more about standard UNIX and ANSI C topics. For this information, consult a computer bookstore or manuals such as:

- AT&T. *UNIX System V Release 4 Programmer's Guide: ANSI C and Programming Support Tools*. Englewood Cliffs, NJ: Prentice Hall, 1990.
- Levine, Mason, and Brown. *lex & yacc*. Sebastopol. CA: O'Reilly & Associates, Inc., 1992.
- Oram and Talbott. *Managing Projects with make*. Sebastopol. CA: O'Reilly & Associates, Inc., 1991.
- American National Standards Institute, Inc. *American National Standard, Programming Language—C, ANSI C Standard*. ANSI X3.159−1989.
- International Standard ISO/IEC. *Programming languagues—C, 9899*. 1990(E).

Conventions Used in This Guide

This guide uses these conventions and symbols:

`Courier`	In text, the Courier font represents function names, file names, and keywords. It is also used for command syntax, output, and program listings.
`bold`	Boldface is used along with Courier font to represent user input.
italics	Words in italics represent characters or numerical values that you define. Replace the abbreviation with the defined value. Also, italics are used for manual titles, manual page names, and commands. The section number, in parentheses, follows the name.
_ _	A double underline appears as __ in text.
[ ]	Brackets enclose optional items.
{ }	Braces enclose two or more items; you must specify at least one of the items.
|	The OR symbol separates two or more optional items.
…	A horizontal ellipsis in a syntax statement indicates that the preceding optional items can appear more than once in succession.
( )	Parentheses enclose entities and must be typed.

The following two examples illustrate the syntax conventions:

```
DIMENSION a(d) [,a(d)] …
```

indicates that the Fortran keyword DIMENSION must be typed as shown, that the user−defined entity *a(d)* is required, and that one or more of *a(d)* can be specified. The parentheses ( ) enclosing *d* are required.

```
{STATIC | AUTOMATIC} v [,v] …
```

indicates that either the STATIC or AUTOMATIC keyword must be typed as shown, that the user−defined entity *v* is required, and that one or more *v* items can be specified.

Chapter 1
About the MIPSpro Compiler System

The IRIX compiler system produces either 64−bit objects or 32−bit objects. This guide describes the MIPSpro compilers that produce 64−bit objects. For information about producing 32−bit objects, refer to the *IRIX System Programming Guide*.

The MIPSpro complier system components enable you to create executable programs using such languages as C, C++, and Fortran 77. **Table 1−1** summarizes the MIPSpro compiler system components and the task each performs.

Table 1−1 Compiler System Functional Components

Tool	Task	Examples
Text editor	Write and edit programs	*vi*, *jot, emacs*
Compiler driver	Compile, link, and load programs	*cc*, *CC, f77*
Object file analyzer	Analyze object files	*dwarfdump, elfump, file*, *nm*, *size, dis*
Profiler	Analyze program performance	*prof*, *pixie*
Archiver	Produce object−file libraries	*ar*
Linker	Link object files	*ld*
Runtime loader	Link Dynamic Shared Objects at runtime	
Debugger	Debug programs	*dbx*

A single program called a compiler driver (such as *cc*, *CC*, or *f77*) invokes the following major components of the compiler system (refer to **Figure 1−1**).

- Macro preprocessor (*cpp*)
- Parallel analyzer (*pca, mpc, fef77p*)
- Scalar optimizer (*copt*)
- Compiler frontend (*fec, fecc*, *fef77*, *fef*77p)
- Compiler back end
- Linker (*ld*)

You can invoke a compiler driver with various options (described later in this chapter) and with one or more source files as arguments. All specified source files are automatically sent to the macro preprocessor.

Although the macro preprocessor was originally designed for C programs, it is now run by default as part of most compilations. To prevent running the preprocessor, use the *-nocpp* option on the driver command line. For C and C++ compilations, preprocessing and front−end compilation is done by *fec* and *fecc*. For all other compilations, preprocessing is done by invocation of a separate executable named *cpp*.

If available, the parallel analyzers *pca* and *fef77p* produce parallelized source code from standard source code. *mpc* takes the output from *pca* and produces parallel C code (part of Power C). The result takes advantage of multiple CPUs (when present) to achieve higher computation rates. *pca* and *mpc* are part of Power C. Power Fortran automatically uses the parallel Fortran compiler, *fef77p*, to produce parallel code. For more information about these packages and how to obtain them, contact your dealer/sales representative.

The compiler front ends (*fec*, *fecc*, *fef77*) translate the source code into an intermediate tree representation. The compiler back end (*be*) translates the intermediate code into object code. The language compilers share the same back end (*be*), which combines optimization and code generation in one phase. (For more information about optimization, see **Chapter 6, "Optimizing Program Performance."**).

The linker *ld* combines several object files into one, performs relocation, and resolves external symbols. The driver automatically runs *ld* unless you specify the *-c* option to skip the linking step.

When you compile or link programs, by default, the compiler searches */usr/lib*, */lib*, and */usr/local/lib*. Certain default libraries are automatically linked. Drivers and their respective libraries are listed in **Table**

1−2 .

Table 1−2 Compilers and Default Libraries

Compiler	**Default LIbraies**
cc	*libc.so*
CC	*libC.so*, *libc.so*
f77	*libftn.so*, *libc.so*, *libm.so*

To see the various utilities a program passes through during compilation, invoke the appropriate driver with the *-show* option.

Figure 1.1 shows compilation flow from source file (to executable file (a.out).



Figure 1−1 Compiler System Flowchart

Chapter 2

Using the MIPSpro Compiler System

This chapter provides information about the MIPSpro compiler system, and describes the object file format and dynamic linking. Specifically, this chapter covers the topics listed below:

- **"Selecting a Compiler"** explains how to specify a 64–bit or 32–bit compilation mode.
- **"Object File Format and Dynamic Linking"** discusses object files including executable and linking format, dynamic shared objects, and position–independent code.
- **"Source File Considerations"** explains source file naming conventions and the procedure for including header files.
- **"Compiler Drivers"** lists and explains general compiler–driver options.
- **"Linking"** explains how to link programs manually (using *ld* or a compiler) and how to compile multilanguage programs. It also covers Dynamic Shared Objects and how to link them into a program.
- **"Debugging"** describes the compiler–driver options for debugging.
- **"Getting Information About Object Files"** provides information on how to use the object file tools to analyze object files.
- **"Using the Archiver to Create Libraries"** explains how to use the archiver, *ar*.

Selecting a Compiler

You can select a compilation mode to compile either 64–bit objects or 32–bit objects by using command–line options and/or setting an environment variable. When determining the compilation mode to use, the system first checks command–line options. Next, it checks the environment variable.

Using Command–Line Options

If you specify the *-32* option to the compiler, the system compiles the source files to 32–bit objects. If you specify the *-64* option on the command line, the system compiles the source files to 64–bit objects.

Setting an Environment Variable

You can set an environment variable to specify the compilation mode to use. To set up your environment for 32–bit compilation, type:

```
setenv SGI_ABI -32
```

To set up your environment for 64–bit compilation, type:

```
setenv SGI_ABI -64
```

If you don't specify *-32* or *-64* on the command line, or don't set an environment variable, the system determines the compilation mode to use.

Object File Format and Dynamic Linking

This section describes how the compiler system

- uses **"Executable and Linking Format"** (ELF) for object files
- uses shared libraries called **"Dynamic Shared Objects"** (DSOs)
- creates **"Position–Independent Code"** (PIC), by default, to support dynamic linking

Executable and Linking Format

The compiler system produces ELF object files. ELF is the format specified by the System V Release 4 Applications Binary Interface (the SVR4 ABI). ELF provides support for Dynamic Shared Objects, described below.

Types of ELF object files are as follows:

- Relocatable files contain code and data in a format suitable for linking with other object files to make a shared object or executable.
- Dynamic Shared Objects contain code and data suitable for *dynamic linking*. Relocatable files may be linked with DSOs to create a dynamic executable. At run time, the run−time linker combines the executable and DSOs to produce a process image.
- Executable files are programs ready for execution. They may or may not be dynamically linked.

COFF executables continue to run on new releases of IRIX, but the current compiler system has no facility for creating or linking COFF executables. COFF and ELF object files may not be linked together. To take advantage of new IRIX features, you must recompile your code.

You can use this version of the compiler system to construct ABI−compliant executables that run on any operating system supporting the MIPS ABI. Be careful to avoid referencing symbols that are not defined as part of the MIPS ABI specification. For more information, see the *System V Applications Binary Interface—Revised Edition* and the *System V ABI MIPS Processor Supplement*.

Dynamic Shared Objects

IRIX uses shared objects called *Dynamic Shared Objects*, or *DSOs*. The object code of a DSO is *position−independent code* (PIC), which can be mapped into the virtual address space of several different processes at once. DSOs are loaded at run time instead of at linking time, by the run−time loader, *rld*. As is true for static shared libraries, the code for DSOs is not included in executable files; thus, executables built with DSOs are smaller than those built with non−shared libraries, and multiple programs may use the same DSO at the same time. For more information on DSOs, see **Chapter 3, "Using Dynamic Shared Objects."**

Static shared libraries are only supported under this release for the purposes of running old (COFF) binaries. The current compiler system has no facilities for generating static shared libraries.

Position−Independent Code

Dynamic linking requires that all object code used in the executable be position−independent code. For source files in high−level languages, you just need to recompile to produce PIC. Assembly language files must be modified to produce PIC; see the *MIPSpro Assembly Language Programmer's Guide* for details.

Position−independent code satisfies references indirectly by using a *global offset table* (GOT), which allows code to be relocated simply by updating the GOT. Each executable and each DSO has its own GOT.

The compiler system produces PIC by default when compiling higher−level language files. All of the standard libraries are provided as DSOs, and therefore contain PIC code; if you compile a program into non−PIC, you will be unable to use those DSOs. One of the few reasons to compile non−PIC is to build a device driver, which doesn't rely on standard libraries; in this case, you should use the *-non_shared* option to the compiler to negate the default option, *-KPIC*. For convenience, the C library and math library are provided in non−shared format as well as in DSO format (although the non−shared versions are not installed by default). You can link these libraries *-non_shared* with other non−PIC files.

Source File Considerations

This section describes conventions for naming source files and including header files. Topics covered include:

- **"Source File Naming Conventions"**
- **"Header Files"**

Source File Naming Conventions

Each compiler driver recognizes the type of an input file by the suffix assigned to the filename. **Table 2−1** describes the possible filename suffixes.

Table 2−1 Driver Input File Suffixes

Suffix	Description
.s	Assembly source

.i	Preprocessed source code in the language of the processing driver
.c	C source
.C, .cxx, .cc, .c++	C++ source
.f, .F, .for, .FOR	Fortran 77 source
.o	Object file
.a	Object library archive
.so	Dynamic shared object library

The following example compiles preprocessed source code:

```
f77 -c tickle.i
```

The Fortran compiler, *f77,* assumes the file *tickle.i* contains Fortran statements (because the Fortran driver is specified). *f77* also assumes the file has already been preprocessed (because the suffix is *.i*), and therefore does not invoke the preprocessor.

Header Files

Header files, also called *include* files, contain information about the libraries with which they're associated. They define such things as data types, data structures, symbolic constants, and prototypes for functions exported by the library. To use those definitions without having to type them into each of your source files, you can use the *#include* directive to tell the macro preprocessor to include the complete text of the given header file in the current source file. When you include header files in your source files you can specify such definitions conveniently and consistently in each source file that uses any of the library routines.

By convention, header filenames have a *.h* suffix. Each programming language handles these files the same way, via the macro preprocessor. For example, the *stdio.h* header file describes, among other things, the data types of the parameters required by *printf()*.

For detailed information about standard header files and libraries, see the International Standard ISO/IEC. *Programming languages—C, 9899*. 1990. Also see **"Using Typedefs"** for information about the *inttypes.h* header file.

Specifying a Header File

The *#include* directive tells the preprocessor to replace the *#include* line with the text of the indicated header file. The usual way to specify a header file is with the line

```
#include <filename>
```

where *filename* is the name of the header file to be included. The angle brackets (< >) surrounding the filename tell the macro preprocessor to search for the specified file only in directories specified by command−line options and in the default header−file directory (*/usr/include*).

Another specification format exists, in which the filename is given between double quotation marks. In this case, the macro preprocessor searches for the specified header file in the current directory first, then (if it doesn't find the requested file) goes on and searches in the other directories as in the angle−bracket specification.

Creating a Header File for Multiple Languages

A single header file can contain definitions for multiple languages; this setup allows you to use the same header file for all programs that use a given library, no matter what language those programs are in.

To set up a shareable header file, create a *.h* file and enter the definitions for the various languages as follows:

```
#ifdef _LANGUAGE_C

C definitions

#endif
```

```
#ifdef _LANGUAGE_C_PLUS_PLUS

C++ definitions

#endif

#ifdef _LANGUAGE_FORTRAN

Fortran definitions

#endif
```

Note: You must specify _LANGUAGE_ before the language name and to indicate C++ definitions, you must use _LANGUAGE_C_PLUS_PLUS, not _LANGUAGE_C++.

You can specify the various language definitions in any order.

Compiler Drivers

The driver commands, such as *cc* and *f77* call subsystems that compile, optimize, assemble, and link your programs. This section describes:

- **"Default Behavior for Compiler Drivers"**
- **"General Options for Compiler Drivers"**

Default Behavior for Compiler Drivers

At compilation time, you can select one or more options that affect a variety of program development functions, including debugging, profiling, and optimizing. You can also specify the names assigned to output files. Note that some options have default values that apply if you do not specify them.

When you invoke a compiler driver with source files as arguments, the driver calls other commands that compile your source code into object code. It then optimizes the object code (if requested to do so) and links together the object files, the default libraries, and any other libraries you specify.

Given a source file *foo.c*, the default name for the object file is *foo.o*. The default name for an executable file is *a.out*. The following example compiles source files *foo.c* and *bar.c* with the default options:

```
cc foo.c bar.c
```

This example produces two object files (*foo.o* and *bar.o*), then links them with the default C library *libc* to produce an executable called *a.out*.

Note: If you compile a single source directly to an executable, the compiler does not create an object file.

General Options for Compiler Drivers

The command–line options for MIPSpro compiler drivers are listed and explained in **Table 2–2** . The table lists only the most frequently used options, not all available options. See the appropriate compiler reference (manual) page for additional details on these commands.

In addition to the general options in **Table 2–2** , each driver has options that you typically won't use. These options primarily aid compiler development work. For information about nonstandard driver options, consult the appropriate driver reference page.

You can use the compiler system to generate profiled programs that, when executed, provide operational statistics. To perform this procedure, use the *-p* compiler option (for pc sampling information) and the *prof* command (for profiles of basic block counts). Refer to **Chapter 5, "Using the Performance Tools,"** for details.

Table 2–2 General Driver Options

Option	Purpose
-32	Generates a 32–bit object.
-64	Generates a 64–bit object. This is the default.
-ansi	Strict ANSI/ISO C compilation mode. Preprocessing adds only standard predefined symbols to the name space, and standard include files declare only standard symbols.
-c	Prevents the linker from linking your program after code generation. This option forces the driver to produce a *.o* file after the back–end phase, and prevents the driver from producing an executable file.
-C	Used with the *-P* or *-E* option. Prevents the macro preprocessor from stripping comments. Use this option when you suspect the preprocessor is not producing the intended code and you want to examine the code with its comments.
-cckr	K&R/Version7 C compatibility compilation mode. Preprocessing may add more predefined symbols to the name space than in *-ansi* mode. Compilation adheres to the K&R language semantics.
-Dname[=*def*]	Defines a macro *name* as if you had specified a *#define* in your program. If you do not specify a definition with *=def*, *name* is set to 1.
-E	Runs only the macro preprocessor and sends results to the standard output. To retain comments, use the *-C* option as well. Use *-E* when you suspect the preprocessor is not producing the intended code.
-fullwarn	Checks code and produces additional warnings that are normally suppressed. This option is recommended for all compiles during software development. You can turn off warnings selectively by using the *-woff* option.
-g[*num*]	Produces debugging information. The default is *-g0*: do not produce debugging information.
-G[*num*]	Specifies the maximum size, in bytes, of a data item that is accessed from the global pointer. The default is *-G8*.
-help	Lists the available compiler options.
-Idirname	Adds *dirname* to the list of directories to be searched for specified header files. These directories are always searched before the default directory, */usr/include*.
-KPIC	Generates position–independent code. This is the default and is required for programs linking with dynamic shared objects. Specify *-non_shared* if you don't want to generate PIC code.
-mips1	Generates code using the instruction set of the MIPS R2000/R3000 RISC architecture. This option implies *-32*.
-mips2	Generates code using the MIPS II instruction set (MIPS I + R4000 specific extensions). Note that code compiled with *-mips2* does not run on R2000/R3000–based machines. This option implies *-32*.
-mips3	Generates code using the full MIPS R4000 instruction set, including 64–bit code. This option implies *-64*.
-mips4	Generates code using the MIPS R8000 instruction set. This option implies

-64.

-nocpp Suppresses running of the macro preprocessor on the source files prior to processing.

-non_shared Turns off the default option,

-KPIC, to produce non−shared code. This code can be linked to only a few standard libraries (such as *libc.a* and *libm.a*) that are provided in non−shared format in the directory */usr/lib/nonshared*. You should use this option only when building device drivers.

-nostdinc Suppresses searching of

/usr/include for the specified header files.

-o filename Names the result of the compilation

filename. If an executable is being generated, it is named *filename* rather than the default name, *a.out*.

-Onum Specifies optimization options.

-O0 turns off optimizations.
-O1 turns on local optimizations that can be done quickly.
*-O*2 (*-O*) turns on global optimizations. This is the default.
-O3 turns on all optimizations.
For more information, see **Chapter 6, "Optimizing Program Performance."**

-OPT:options Controls optimization options. For more information, see

Chapter 6, "Optimizing Program Performance."

-p Sets up for profiling by periodically sampling the value of the program counter (only effects the loading).

-P Runs only the macro preprocessor on the files and puts the result of each file in a

.i file. Specify both *-P* and *-C* to retain comments.

-S Similar to

-c, except that it produces assembly code in a *.s* file instead of object code in a *.o* file. *-S* provides information about the code and comments about such things as software pipelining, the loops it works on, and the results.

-show Lists compiler phases as they are executed. Use this option to see the default options for each compiler phase along with the options you've specified.

-SWP:options Controls software pipelining of inner loops. For more information, see

Chapter 6, "Optimizing Program Performance."

-TARG:options Controls the target architecture and machine for which code is generated. For more information, see

Chapter 6, "Optimizing Program Performance."

-TENV:options Controls the target environment assumed by the compiler. For more information, see

Chapter 6, "Optimizing Program Performance."

-Uname Overrides a definition of the macro

name that you specified with the *-D* option, or that is defined automatically by the driver. Note that this option does not override a macro definition in a source file, only on the command line.

-woff n Suppresses ANSI/ISO warning message number

n. Suppress multiple warning numbers by using a comma−separated list (*-woff n1,n2*...), a range of warning numbers by using a hyphen−separated list (*-woff n1−n5*), or any combination thereof. You can suppress all warning messages via *-woff all.*

-xansi Compilation follows an extended ANSI/ISO C language semantics, which is more lenient in terms of the forms of expressions it allows. Preprocessing combines predefined macros. This is the default C compilation mode.

Note: To use 4.3 BSD extensions in C, compile using *-xansi* or by using the -D__EXTENSIONS__ option on the command line. For example:

```
cc prog.c −ansi −prototypes −fullwarn −lm −D__EXTENSIONS__
```

Linking

The linker, *ld*, combines one or more object files and libraries (in the order specified) into one executable file, performing relocation, external symbol resolutions, and all other required processing. Unless directed otherwise, the linker names the executable file *a.out*.

This section summarizes the functions of the linker. It also covers how to link a program manually (without using a compiler driver) and how to compile multilanguage programs. Refer to the *ld*(1) reference page for complete information on the linker. Specifically, this section describes:

- **"Invoking the Linker Manually"**
- **"Linking Assembly Language Programs"**
- **"Linking Libraries"**
- **"Linking to Previously Built Dynamic Shared Objects"**
- **"Linking Multilanguage Programs"**

Invoking the Linker Manually

Usually the compiler invokes the linker as the final step in compilation (as explained in **"Compiler Drivers"**). If object files exist that were produced by previous compilations, and you want to link them, invoke the linker by using a compiler driver instead of calling *ld* directly. Just pass the object filenames to the compiler driver in place of source filenames. If the original source files are in a single language, simply invoke the associated driver and specify the list of object files. (For information about linking objects derived from several languages, see **"Linking Multilanguage Programs."**)

A few command−line options to *ld*, such as *-p*, have different meanings when used as command−line options to *cc*. To pass such options to *ld* through an invocation of a compiler driver, use the *-Wl* option to the driver (see the reference page for details).

Typically, the compiler driver invokes *ld* as necessary. Circumstances exist under which you may need to invoke *ld* directly, such as when you're building a shared object or doing special linking not supported by compiler drivers (such as building an embedded system). To build C++ shared objects, use the CC driver.

Linker Syntax

A summary of *ld* syntax follows.

```
ld options   object1 [object2...objectn]
```

options One or more of the options listed in **Table 2−3** .
object Specifies the name of the object file to be linked.

Table 2−3 contains only a partial list of linker options. Many options that apply only to creating shared objects are discussed in **Chapter 3, "Using Dynamic Shared Objects."** For complete information on options and libraries that affect linker processing, refer to the *ld*(1) reference page.

Table 2−3 Linker Options

Option	Purpose

-32	Links 32–bit programs and DSOs.
-64	Links 64–bit programs and DSOs.
-lname	Specifies the name of a library, where *lname* is the library name. The linker searches for *lname.so* (and then *lname.a*) first in any directories specified by *-L dirname* options, and then in the standard directories: */usr/lib*, */lib*, and */usr/local/lib*.
-L dirname	Adds *dirname* to the list of directories to be searched for (as well as libraries searched for) as specified by subsequent *-lname* options.
-m	Produces a linker memory map, listing input and output sections of the code, in System V format.
-M	Produces a link map in BSD format, listing the names of files to be loaded.
-nostdlib	This option must be accompanied by the *-L dirname* option. If the linker does not find the library in *dirname* list, then it does not search any of the standard library directories.
-o filename	Specifies a name for your executable. If you do not specify *filename*, the linker names the executable *a.out*.
-s	Strips debugging information from the program object, reducing its size. This option is useful for linking routines that are frequently linked into other program objects, but may hamper debugging.
-v	Produces verbose linker output providing information about various linker passes.
-ysymname	Reports all references to, and definitions of, the symbol *symname*. Useful for locating references to undefined symbols.

Linker Example

The following command tells the linker to search for the DSO *libcurses.so* in the directory */usr/lib*. If it does not find that DSO, the linker then looks for *libcurses.a* in */lib*.

```
ld foiled.o again.o –lcurses
```

If the linker doesn't find an appropriate library, it looks in */usr/local/lib* for *libcurses.a*. (Note that the linker does not look for DSOs in */usr/local/lib*, so don't put shared objects there.) If found in any of these places, the DSO or library is linked with the objects *foiled.o* and *again.o*; otherwise an error is generated.

Linking Assembly Language Programs

The assembler driver (*as*) does not run the linker. To link a program written in assembly language, use one of these procedures:

- Assemble and link using one of the other driver commands (*cc*, for example). The *.s* suffix of the assembly language source file causes the driver to invoke the assembler.
- Assemble the file using *as*; then link the resulting object file with the *ld* command.

Linking Libraries

The linker processes its arguments from left to right as they appear on the command line. Arguments to *ld* can be DSOs, object files, or libraries.

When *ld* reads a DSO, it adds all the symbols from that DSO to a cumulative symbol table. If it encounters a symbol that's already in the symbol table, it does not change the symbol table entry. If you define the same symbol in more than one DSO, only the first definition is used.

When *ld* reads an archive, usually denoted by a filename ending in *.a*, it uses only the object files from that archive that can resolve currently unresolved symbol references. (When a symbol is referred to but not defined in any of the object files that have been loaded so far, it's called unresolved.) Once a library has been searched in this way, it is never searched again. Therefore, libraries should come after object files on the command line in order to resolve as many references as possible. Note that if a symbol is already in the cumulative symbol table from having been encountered in a DSO, its definition in any subsequent archive or DSO is ignored.

Specifying Libraries and DSOs

You can specify libraries and DSOs either by explicitly stating a pathname or by use of the library search rules. To specify a library or DSO by path, simply include that path on the command line (relative to the current directory, or else absolute):

```
ld myprog.o /usr/lib/libc.so.1 mylib.so
```

libc.so.1 is the name of the standard C DSO, replacing the older *libc.a*. Similarly, *libX11.so.1* is the X11 DSO. Most other DSOs are simply named *name.so*, without a *.1* extension.To use the linker's library search rules, specify the library with the *-lname* option:

```
ld myprog.o −lmylib
```

When the *-lmylib* argument is processed, *ld* searches for a file called *libmylib.so*. If it can't find *libmylib.so* in a given directory, it tries to find *libmylib.a* there; if it can't find that either, it moves on to the next directory in its search order. The default search order is to look first in */usr/lib*, then in */lib*.

If *ld* is invoked from one of the compiler drivers, all *-L* and *-nostdlib* options are moved up on the command line so that they appear before any *-lname* option. For example, consider the command:

```
cc file1.o −lm −L mydir
```

This command invokes, at the linking stage of compilation, the following:

```
ld −L mydir file1.o −lm
```

Note: There are three different kinds of files that contain object code files: non−shared libraries, PIC archives, and DSOs. Non−shared libraries are the old−style library, built using *ar* from *.o* files that were compiled with *-non_shared*. These archives must also be linked *-non_shared*. PIC archives are the default, built using *ar* from *.o* files compiled with *-KPIC* (the default option); they can be linked with other PIC files. DSOs are built from PIC *.o* files by using *ld -shared*; see **Chapter 3** for details.

If the linker tells you that a reference to a certain function is unresolved, check that function's reference page to find out which library the function is in. If it isn't in one of the standard libraries (which *ld* links in by default), you may need to specify the appropriate library on the command line. For an alternative method of finding out where a function is defined, see **"Finding an Unresolved Symbol With ld."**

Note: Simply including the header file associated with a library routine is not enough; you also must specify the library itself when linking (unless it's a standard library). No automatic connection exists between header files and libraries; header files only give prototypes for library routines, not the library code itself.

Examples of Linking DSOs

To link a sample program *foo.c* with the math DSO, *libm.so*, enter:

```
cc foo.c −lm
```

To specify the appropriate DSOs for a graphics program *foogl.c*, enter:

```
cc foogl.c −lgl −lX11
```

Linking to Previously Built Dynamic Shared Objects

This section describes how to link your source files with previously built DSOs; for more information about how to build your own DSOs, see **Chapter 3, "Using Dynamic Shared Objects."**

To build an executable that uses a DSO, call a compiler driver just as you would for a non−shared library. For instance,

```
cc needle.c −lthread
```

This command links the resulting object file (*needle.o*) with the previously built DSO *libthread.so* (and the standard C DSO, *libc.so.1*), if available. If no *libthread.so* exists, but a PIC archive named *libthread.a* exists, that archive is used with *libc.so.1*, so you still get dynamic (run time) linking. Note that even *.a* libraries now contain position−independent code by default, though it is also possible to build non−shared *.a* libraries that do not contain PIC.

Linking Multilanguage Programs

The source language of the main program may differ from that of a subprogram. In this case, you can link multilanguage programs.

Follow the steps below to link multilanguage programs. (Refer to **Figure 2−1** for an illustration of the process.)

1. Compile object files from the source files of each language separately by using the *-c* option.

   For example, if the source consists of a Fortran main program (*main.f*) and two files of C functions (*more.c* and *rest.c*), use the commands:

   ```
   cc −c more.c rest.c
   f77 −c main.f
   ```

   These commands produce the object files *main.o, more.o,* and *rest.o*.

2. Use the compiler associated with the language of the main program to link the objects:

   ```
   f77 main.o more.o rest.o
   ```

   The compiler drivers supply the default set of libraries necessary to produce an executable from the source of the associated language. However, when producing executables from source code in several languages, you may need to specify the default libraries explicitly for one or more of the languages used. For instructions on specifying libraries, see **"Linking Libraries."**



Figure 2−1 Compilation Control Flow for Multilanguage Programs

Use caution when passing pointers and longs between languages as some languages use different type sizes and structures for data types.For specific details about compiling multilanguage programs, refer to the programming guides for the appropriate languages.

Finding an Unresolved Symbol With *ld*

You can use *ld* to locate unresolved symbols. For example, suppose you're compiling a program, and *ld* tells you that you're using an unresolved symbol. However, you don't know where the unresolved symbol is referenced.

To find the unresolved symbol, enter:

```
ld −ysymbol file1... filen
```

You can also enter:

```
cc prog.o −Wl,−ysymbol
```

The output lists the source file that references *symbol*.

Debugging

The compiler system provides a debugging tool, *dbx*, described fully in **Chapter 4, "Using the Debugger."** Before using *dbx*, specify the *-g* driver option (see **Table 2−4**) to produce executables containing information that the debugger can use.

Table 2−4 Driver Options for Debugging

Option	Purpose
-g0	Produces a program object with a minimum of source−level debugging information. This is the default. Reduces the size of the program object but allows optimizations. Use this option with the *-O* option after you finish debugging.
-g, *-g2*	Produces additional debugging information for full symbolic debugging. This option overrides the optimization options (*-Onum*).
-g3	Produces additional debugging information for full symbolic debugging of fully optimized code. This option makes the debugger less accurate. You can use *-g3* with an optimization option (*-Onum*).

Getting Information About Object Files

The following tools provide information on object files:

- *dis* disassembles an object file into machine instructions.
- *dwarfdump* lists headers, tables, and other selected parts of a DWARF−format object file or archive file.
- *elfdump* lists the contents (including the symbol table and header information) of an ELF−format object file.
- *file* provides descriptive information on the properties of a file.
- *nm* lists symbol table information.
- *size* prints the size of each section of an object file (some such sections are named *text*, *data*, and *sbss*).
- *strip* removes symbol table and relocation bits.

Disassembling Object Files with *dis*

The *dis* tool disassembles object files into machine instructions. You can disassemble an object, archive library, or executable file.

dis Syntax

```
dis options   filename1   [filename2...filenamen]
```

options One or more of the options listed in **Table 2−5** .
filename Specifies the name of one or more files to disassemble.

dis Options

Table 2−5 lists *dis* options. For more information, see the *dis*(1) reference page.

Table 2−5 *dis* Options

Option	Description
-b begin_address	Starts disassembly at *begin_address*. You can specify the address as decimal, octal (with a leading *0*), or hexadecimal (with a leading *0x*).
-d section	Disassembles the named *section* as data, and prints the offset of the data from the beginning of the section.
-D section	Disassembles the named *section* as data, and prints the address of the data.
-e end_address	Stops disassembly at *end_address*. You can specify the address as decimal, octal (with a leading *0*), or hexadecimal (with a leading *0x*).
-F function	Disassembles the named *function* in each object file you specify on the command line.
-h	Substitutes the hardware register names for the software register names in the output.
-H	Removes the leading source line, and leaves the hex value and the instructions.
-i	Removes the leading source line and hexadecimal value of disassembly, and leaves only the instructions.
-I directory	Uses *directory* to help locate source code.
-l string	Disassembles the archive file specified by *string*.
-L	Looks up source labels for subsequent printing.
-o	Prints numbers in octal. The default is hexadecimal.
-s	Performs symbolic disassembly where possible. Prints (using C syntax) symbol names on the line following the instruction. Displays source code mixed with assembly code
-t section	Disassembles the named *section* as text.
-T	Specifies the trace flag for debugging the disassembler.
-V	Prints (on *stderr*) the version number of the disassembler being executed.
-w	Prints source code to the right of assembly code (produces wide output). Use this option with the *-s* option.
-x	Prints offsets in hexadecimal (the default).

Listing Parts of DWARF Object Files With *dwarfdump*

The *dwarfdump* tool provides debugging information from selected parts of DWARF symbolic information in an Elf object file. For more information on DWARF, see files in the *4Dgifts* directory.

dwarfdump Syntax

```
dwarfdump options   filename
```

options One or more of the options listed in **Table 2−6** .
filename Specifies the name of the object file whose contents are to be dumped.

dwarfdump Options

Table 2−6 lists *dwarfdump* options. For more information, see the *dwarfdump*(1) reference page.

Table 2−6 *dwarfdump* Options

Option	Dumps
-a	All sections.
-b	The *.debug_abbrev* section.

-c	The *.debug_loc* section.
-d	Uses dense mode. Prints die information of the *.debug_info* section. Does not imply the *-i* option.
-e	Uses ellipsis mode. Uses the short names for DW_TAG_* and DW_ATTR_* in the output for the *.debug_info* section.
-f	The *.debug_frame* section.
-i	The *.debug_info* section.
-l	The *.debug_line* section.
-m	The *.debug_macinfo* section.
-o	The *.rel.debug_** sections.
-p	The *.debug_pubnames* section.
-r	The *.debug_aranges* section.
-s	The *.debug_string* section.
-ta	The *.debug_static_funcs* and *.debug_static_vars* sections (same as *-tfv*).
-tf	The *.debug_static_funcs* section.
-tv	The *.debug_static_vars* section.
-u file	Sections to the named *file*.
-v	Prints detailed information (verbose mode).
-w	The *.debug_weaknames* section.
-y	The *.debug_types* section.

Listing Parts of ELF Object Files and Libraries with *elfdump*

The *elfdump* tool lists headers, tables, and other selected parts of an ELF−format object file or archive file.

elfdump Syntax

```
elfdump options   filename1   [filename2...filenamen]
```

options	One or more of the options listed in **Table 2−7** .
filename	Specifies the name of one or more object files whose contents are to be dumped.

elfump Options

Table 2−7 lists *elfdump* options. For more information, see the *elfdump*(1) reference page.

Table 2−7 *elfdump* Options

Option	Dumps
-a	Archive header of each member of the archive.
-A	Beginning address of a section.
-c	String table.
-C	Decoded C++ symbol names.
-cmt	The *.comment* sections.
-cnt	The *.content* sections.
-d	Range of sections.
-Dc	Conflict list in Dynamic Shared Objects.
-Dg	Global Offset Table in Dynamic Shared Objects.
-Dinfo	The *.MIPS.dclass* section.
-Dinst	The *.MIPS.inst* section.
-Dl	Library list in Dynamic Shared Objects.
-Dsym	The *.MIPS.sym* section.
-Dsymlib	Symbol library table (*.MIPS.symlib*).
-Dt	String table entries of the dynamic symbol table in Dynamic Shared Objects.
-e	Events sections.
-f	Each file header.
-F	Literal tables (*.lit4* and *.lit8* sections).
-g	Archive symbol table.
-G	The global pointer table information.
-h	All section headers in the file.

-hash	Hash table entries.
-i	The *.interp* section, which lists the path name of the program interpreter.
-info	Prints whether the object is marked quickstart, or is corded and is marked requickstart.
-l	The *.line* section.
-L	Dynamic linking information in Dynamic Shared Objects.
-n	The specified section (such as .MIPS.content, .dynamic, .got, MIPS.sym, .liblist, .conflict, .reginfo, and so forth).
-o	Each program execution header.
-op	Options section.
-p	Suppresses the printing of headings.
-r	Relocation information.
-R	Register information.
-reg	The *.reginfo* section.
-rpt	The run−time procedure table.
-s	Section contents.
-svr4	Information in SVR4−style format.
-t	Symbol table entries.
-T	Symbol table range.
-u	Updates a COFF file to an ELF file.
-v	Prints detailed information (verbose mode).
-V	Version information only.

Determining File Type with *file*

The *file* tool lists the properties of program source, text, object, and other files. This tool attempts to identify the contents of files using various heuristics. It is not exact and often erroneously recognizes command files as C programs. For more information, see the *file*(1) reference page.

file Syntax

```
file filename1   [filename2...filenamen]
```

Each *filename* is the name of a file to be examined.

file Example

Information given by *file* is self−explanatory for most kinds of files, but using *file* on object files and executables gives somewhat cryptic output. In this example, "MSB" indicates Most Significant Byte, also called Big−Endian; "relocatable" means the object contains relocation information that allows it to be linked with other objects to form an executable; "executable" means an executable file; and "dynamic lib" indicates a DSO.

```
file test.o a.out /lib/libc.so.1
test.o:         ELF 64−bit MSB relocatable MIPS − version 1
a.out:          ELF 64−bit MSB executable MIPS − version 1
/lib/libc.so.1:   ELF 64−bit MSB dynamic lib MIPS − version 1
```

Listing Symbol Table Information: *nm*

The *nm* tool lists symbol table information for object files and archive files.

nm Syntax

```
nm options   filename1 [filename2...filenamen]
```

options	One or more of the options listed in **Table 2−8** .
filename	Specifies the object files or archive files from which symbol table information is to be extracted. If you do not specify a filename, *nm* assumes the file is named *a.out*.

nm Symbol Table Options

Table 2−8 lists *nm* symbol table options. For more information, see the *nm*(1) reference page.

Table 2−8 Symbol Table *nm* Options

Option	Purpose
-a	Prints debugging information.
-A	Prints the listing in System V format (default).
-b	Prints the value field in octal.
-B	Prints the listing in BSD format.
-C	Prints decoded C++ names.
-d	Prints the value field in decimal (the default for System V output).
-g	Prints globally visible names.
-h	Suppresses printing of headers.
-l	Produces a long listing.
-n	Sorts external symbols by name for System V format. Sorts all symbols by value for BSD format (by name is the BSD default output).
-o	Prints value field in octal (System V output). Prints the filename immediately before each symbol name (BSD output).
-p	Produces easily parsible, terse output similar to the BSD format.
-r	Prepends the name of the object file or archive to each output line.
-T	Truncates characters in exceedingly long symbol names; inserts an asterisk as the last character of the truncated name. This option may make the listing easier to read.
-u	Prints only undefined symbols.
-v	Sorts external symbols by value (default for BSD format).
-V	Prints the version number of *nm*.
-x	Prints the value field in hexadecimal.

Table 2−9 defines the one−character codes shown in an *nm* listing. Refer to the example that follows the table for a sample listing.

Table 2−9 Character Code Meanings

Key	Description
a	Local absolute data
A	External absolute data
b	Local zeroed data
B	External zeroed data
C	Common data
d	Local initialized data
D	External initialized data
E	Small common data
G	External small initialized data
N	Nil storage class (unused external reference)
r	Local read−only data
R	External read−only data
s	Local small zeroed data
S	External small zeroed data
t	Local text
T	External text
U	External undefined data
V	External small undefined data

nm Example of Obtaining a Symbol Table Listing

This example demonstrates how to obtain a symbol table listing. Consider the following program, *tnm.c*:

```
#include <stdio.h>
#include <math.h>
#define LIMIT 12
int unused_item = 14;
double mydata[LIMIT];
```

```
main()
{
	int i;
	for(i = 0; i < LIMIT; i++) {
	    mydata[i] = sqrt((double)i);
	}
	return 0;
}
```

Compile the program into an object file by entering:

`cc -c tnm.c`

To obtain symbol table information for the object file *tnm.o* in BSD format, use the *nm -B* command:

```
0000000000 T main
0000000000 B mydata
0000000000 U sqrt
0000000000 D unused_item
00000000 N _bufendtab
```

To obtain symbol table information for the object file *tnm.o* in SVR4 format, use the *nm* command without any options:

```
Symbols from tnm.o:

[Index]   Value     Size    Class    Type         Section    Name

[0]      |         0|        |File    |ref=4        |Text      | tnm.c
[1]      |         0|        |Proc    |end=3 int    |Text      | main
[2]      |       116|        |End     |ref=1        |Text      | main
[3]      |         0|        |End     |ref=0        |Text      | tnm.c
[4]      |         0|        |File    |ref=6        |Text      |
 /usr/include/math.h
[5]      |         0|        |End     |ref=4        |Text      |
 /usr/include/math.h
[6]      |         0|        |Global  |             |Data      | unused_item
[7]      |         0|        |Global  |             |Bss       | mydata
[8]      |         0|        |Proc    |ref=1        |Text      | main
[9]      |         0|        |Proc    |             |Undefined| sqrt
[10]     |         0|        |Global  |             |Undefined| _gp_disp
```

Determining Section Sizes with *size*

The *size* tool prints information about the sections (such as *text*, *rdata*, and *sbss*) of the specified object or archive files. The *elf*(4) reference page describes the format of these sections.

size Syntax

size *options*   [*filename1*   *filename2...filenamen*]

options Specifies the format of the listing (see **Table 2–10**).

filename Specifies the object or archive files whose properties are to be listed. If you do not specify a filename, the default is *a.out*.

size Options

Table 2–10 lists *size* options. For more information, see the *size*(1) reference page.

Table 2–10 *size* Options

Option	Action
-A	Prints data section headers in System V format (default).

-B	Prints output in BSD−style format.
-d	Prints sizes in decimal (default).
-f	Prints data on allocatable sections including the size, permission flags, and the total of the loadable sizes.
-F	Prints data on loadable segments including the name and the total of the section sizes.
-n	Prints nonloadable and nonallocatable section sizes.
-o	Prints sizes in octal.
-svr4	Prints output in SVR4−style format.
-V	Prints the version of size that you are using.
-x	Prints sizes in hexadecimal.

Size Example

An example of the *size* command and the listings produced follows.

`size a.out`

```
   Section         Size           Physical               Virtual
                                   Address               Address
         .interp     21           268435856             268435856
   .MIPS.options    104           268435880             268435880
        .dynamic    464           268435984             268435984
        .liblist     20           268436448             268436448
    .MIPS.symlib     30           268436468             268436468
           .msym    240           268436500             268436500
         .dynstr    312           268436744             268436744
         .dynsym    720           268437056             268437056
           .hash    256           268437776             268437776
     .MIPS.stubs     56           268438032             268438032
           .text    460           268438088             268438088
           .init     24           268438548             268438548
           .data     17           268505088             268505088
          .sdata      8           268505108             268505108
            .got    112           268505120             268505120
            .bss     36           268505232             268505232
```

Removing Symbol Table and Relocation Bits with *strip*

The *strip* tool removes symbol table and relocation bits that are attached to the assembler and loader. Use *strip* to save space after you debug a program. The effect of *strip* is the same as that of using the *−s* option to *ld*.

strip Syntax

strip *options* *filename1* [*filename2...filenamen*]

options	One or more of the options listed in **Table 2−11** .
filename	Specifies the name of one or more object files whose contents are to be stripped.

For more information, see the *strip*(1) reference page.

Table 2−11 *strip* Options

Option	Description
-l	Strips line number information, and keeps the symbol table and debugging information.
-o filename	Puts the stripped information in the *filename* that you specify.
-V	Prints the version number of *strip*.
-x	Keeps symbol table information, but may strip debugging and line number information.

Using the Archiver to Create Libraries

An archive library is a file that includes the contents of one or more object (*.o*) files. When the linker (*ld*) searches for a symbol in an archive library, it loads only the code from the object file where that symbol was defined (not the entire library) and links it with the calling program.

The archiver (*ar*) creates and maintains archive libraries and has the following main functions:

- Copying new objects into the library
- Replacing existing objects in the library
- Moving objects around within the library
- Extracting individual objects from the library
- Creating a symbol table for the linker to search symbols

The following section explains the syntax of the *ar* command and lists some examples of how to use it. See the *ar*(1) reference page for details.

Note: *ar* simply strings together whatever object files you tell it to archive; thus, it can be used to build either non–shared or PIC libraries, depending on how the included *.o* files were built in the first place. If you do create a non–shared library with *ar*, remember to link it *-non_shared* with your other code. For information about building DSOs and converting libraries to DSOs, see **Chapter 3** .

ar Syntax

`ar options [posObject] libName [object1...objectn]`

options	Specifies the action that the archiver is to take. **Table 2–12** and **Table 2–13** list the available options. To specify more than one option, don't use a dash or put spaces between the options. For example, use *ar ts*, not *ar -t -s*.
posObject	Specifies the name of an object within an archive library. It specifies the relative placement (either before or after *posObject*) of an object that is to be copied into the library or moved within the library. This parameter is required when the *a*, *b*, or *i* suboptions are specified with the *m* or *r* option. The last example in **"ar Examples,"** shows the use of a *posObject* parameter.
libName	Specifies the name of the archive library you are creating, updating, or extracting information from.
object	Specifies the name(s) of the object file(s) to manipulate.

ar Options

When running the archiver, specify exactly one of the options *d*, *m*, *p*, *q*, *r*, *t*, or *x* (listed in **Table 2–12**). In addition, you can optionally specify any of the modifiers in **Table 2–13** .

Table 2–12 Archiver Options

Option	Purpose
d	Deletes the specified objects from the archive.
f	Adds padding to the end of each object file archived, using the character *\n*. This enables the loader to have faster access to members in the archive while performing static linking. *Warning*: This option results in a permanent change in the size of object files.
p	Prints the specified objects in the archive on the standard output device (usually the terminal screen).
q	Adds the specified object files to the end of the archive. This option is similar to the *r* option (described below), but is faster and does not remove any older versions of the object files that may already be in the archive. Use the *q* option when creating a new library.
r	Adds the specified object files to the end of the archive file. If an object file with the same name already exists in the archive, the new object file overwrites it. Use the *r* option when updating existing libraries.
t	Prints a table of contents on the standard output (usually the screen) for the specified object or archive file.
x	Copies the specified objects from the archive and places them in the current directory.

Duplicate files are overwritten. The last modified date is the current date (unless you specify the *o* suboption, in which case the date stamp on the archive file is the last modified date). If no objects are specified, x copies all the library objects into the current directory.

Table 2−13 Archiver Modifiers

Option	Purpose
c	Suppresses the warning message that the archiver issues when it discovers that the archive you specified does not already exist.
l	Puts the archiver's temporary files in the current working directory. Ordinarily, the archiver puts those files in */tmp* (unless the STMDIR environment variable is set, in which case *ar* stores temporary files in the directory indicated by that variable). This option is useful when */tmp* (or STMDIR) is full.
s	Creates a symbol table in the archive. This modifier is rarely necessary since the archiver updates the symbol table of the archive library automatically. Options *p*, *q*, and *r*, in particular, create a symbol table by default and thus do not require *s* to be specified.
v	Lists descriptive information during the process of creating or modifying the archive. When specified with the *t* option, produces a verbose table of contents.

ar Examples

To create a new library, *libtest.a*, and add object files to it, enter:

```
ar cq libtest.a mcount.o mon1.o string.o
```

The *c* option suppresses an archiver message during the creation process. The *q* option creates the library and puts *mcount.o*, *mon1.o*, and *string.o* into it.

To replace an object file in an existing library, enter:

```
ar r libtest.a mon1.o
```

The *r* option replaces *mon1.o* in the library *libtest.a*. If *mon1.o* does not already exist in the library *libtest.a* , it is added.

Note: If you specify the same file twice in an argument list of files to be added to an archive, that file appears twice in the archive.

Chapter 3

Using Dynamic Shared Objects

A dynamic shared object (DSO) is an object file that's meant to be used simultaneously—or *shared*—by multiple applications (*a.out* files) while they're executing. This chapter contains the following sections:

- **"Using DSOs"** tells you how to obtain the most benefit from using DSOs when creating your executable.
- **"Taking Advantage of QuickStart"** discusses an optimization you can use to make sure that the DSOs you build load as quickly as possible.
- **"Building DSOs"** describes how to build a DSO.
- **"Run−Time Linking"** discusses the run−time linker, and how it locates DSOs at run time.
- **"Dynamic Loading Under Program Control"** explains the use of *dlopen()* *and dlsym()* to control run−time linking.
- **"Versioning of DSOs"** discusses a versioning mechanism for DSOs that allows binaries linked against different, incompatible versions of the same DSO to run correctly.

You can use DSOs in place of archive libraries (they replace static shared libraries provided with earlier releases of IRIX).

Since DSOs contain shared components, using them provides several substantial benefits. First, overall memory usage is minimized because code is shared. Two executables that use the same DSO and that run simultaneously will have only one copy of the instruction from the shared component loaded into memory. For example, if executable A and executable B both link with the same DSO C, and if A and B are both running at the same time, the total memory used is what's required for A, B, and C, plus some small overhead. If C was an unshared library, the memory used would be what's required for A, B, and two copies of C.

A related second benefit is that executables linked with DSOs are smaller than those linked with unshared libraries because the shared objects aren't part of the executable file image, so disk usage is minimized.

Yet another feature of DSOs is that they are much easier to use, build, and debug than static shared libraries. Most of the libraries supplied by Silicon Graphics are available as DSOs. In the past, only a few static shared libraries have been available; most libraries were unshared.

Additionally, executables that use a DSO don't have to be relinked if the DSO changes; when the new DSO is installed, the executable automatically starts using it. This feature makes it easier to update end users with new software versions. It also allows you to create hardware−independent software packages more easily.

Suppose, for example, you want to build both MipsIV and a MipsIII versions of a shared object. You want your program to use the MipsIV version when it is running on a Power Challenge (R8000) system, and also run correctly on another 64−bit platform. Suppose you want to do the above with the routines in as library named *libchange.so*. To do this, build one version of the routines in *libchange* using the *-mips4* option, and place it in */usr/lib64/mips4* on a Power Challenge system. Next, build another version using the *-mips3* option, and place it in */usr/lib64*. Then, when you build an executable that uses *libchange*, use the *-rpath* option to tell the run−time linker to look first for MipsIV versions of the libraries. For example:

```
cc −mips3 −o myprog myprog.o −rpath /usr/lib64/mips4 −lchange
```

As a result, *myprog* runs on any IRIX 6.0 system, and it automatically takes advantage of any MipsIV libraries whenever it runs on a Power Challenge system.

Finally, DSOs and the executables that use them are mapped into memory by a run−time loader, *rld*, which resolves external references between objects and relocates objects at run time. (DSOs contain only position−independent code [PIC], so they can be loaded at any virtual address at run time.) With *rld*, the binding of symbols can be changed at run time at the request of the executing program. You could use this feature to dynamically change the feature set presented to a user of your application, for example, while minimizing start−up time. The application could be started quickly, with a subset of the features available and then, if the user needs other features, those can be loaded in under programmatic control.

Naturally, some costs are involved with using DSOs, and these are explained in the next section, **"Using DSOs."** The sections after that explain how to build and optimize DSOs and how *rld* works. The *dso*(5) reference page also contains more information about DSOs.

Using DSOs

Using DSOs is easy—the syntax is the same as for an archive (*.a*) library. The following compile line creates the executable *yourApp* by linking with the DSOs *libyours.so* and with *libc.so.1*:

```
cc yourApp.c −o yourApp −lyours
```

If *libyours.so* isn't available, but the archive version *libyours.a* is available, that archive version is used along with *libc.so.1*.

A significant difference exists between DSOs and archive libraries in terms of what is mapped into the address space when an application is executing. With an archive library, only the text portion of the library that the application actually requires (and the data associated with that text) is mapped, not the entire library. In contrast, the entire DSO that's linked is mapped; in many cases, however, the DSO is shared and already mapped into the address space. Thus, to conserve address space and save time at startup, don't link with DSOs unless your application actually needs them.

Avoid listing any archive libraries on the compile line after you list shared libraries; instead, list the archive libraries first and then the DSOs.